## Getting Started Getting Started with Nicecast 1. Register on VosCast.com

The first step to starting your own online radio station is purchasing radio hosting!

You can do this right here on VosCast.com. Head over to the <u>plans</u> page to get started.

Now, you may be wondering which plan to choose. This depends mostly on your budget.

128Kb/s will sound the best, and 24Kb/s will sound the worst.

If you have a low budget, we recommend 48Kb/s. However, for the best quality, go with 128Kb/s.

Go to the Plans Page (New window)

#### 2. Set up Your Computer for Broadcasting

Now that you have a SHOUTcast server, you're ready to start streaming. The following steps will outline what you need to do to start streaming live. This tutorial is for Mac OS X.

#### a. Install Nicecast

You can download and purchase Nicecast from Rogue Amoeba's website.

#### **b.** Configure Nicecast for streaming

1. Launch Nicecast

0 0 0	Nicecast Broadcast			
Broadcast	Nicecast 🔗			
Start Broadcast State: Standby Level: Current Track: N/A				
Source	fo Titles Quality Share Effects			

2. By default, Nicecast will select iTunes as the audio source. In most cases this will be the correct source for you, however you can change it by going clicking the "Source" button.

Source	<ul> <li>Nicecast will broadcast audio from the item selected below.</li> </ul>
Application	
@ iTunes	
	Advanced Select

3. Click the "Quality" button. Select the bitrate of your plan and the channel (Stereo or Mono audio) you wish to stream in.

Quality	Determines	s your stream's qualit	y and CPU usage. —
Preset: 🕒	ligh (DSL/Cable Mod	lem)	\$
1	Bitrate:	128 Kbps	\$
:	Sample Rate:	44.100 Khz	\$
	Channels:	Stereo	\$
	CPU Usage/Quality:		
		Least	Most

4. Click "Window" in the menu bar and select "Show Server".

Close Minimize	жW	
Hide Broadcast	₩1	
Show Server	<b>業2</b>	
Show Effects	ж3	
Show Archiving	₩4	
Bring All to Front		
✓ Nicecast Broadcast		

5. In the sidebar, click the "+" button to add a new server.

Servers	
•	ኛ Built-In Server
+	-

6. Type in your VosCast account information and make sure your new server is selected in the sidebar.

00	Nicecast Server	
Server		Nicecast 🔗
	VosCast Guide Server	
Name:	VosCast Guide Server	
Server Type:	Shoutcast	
Account:		
Password:	•••••	
Address:	s1.voscast.com	
Port:	8000	
Mount Point:		
Public URL:	Automatic	

7. Close the server window and go back to the main Nicecast window. Now you can start broadcasting!

Unique solution ID: #1027 Author: Joseph D Last update: 2011-07-02 17:33